

LinuxFocus article number 317 http://linuxfocus.org



by Sebastian Bauer <sebastian.baua(at)t-online.de>

About the author:

At the beginnig of my time at university I unintentionally "crashed" head on into Linux. Since then I learned quite a bit and like the freedom and the possibilities one has with Linux and open source. You can visit my homepage at www.goblin.kicks-ass.org

An ISDN - Fax with Linux



Abstract:

In this article I will describe how to use your linux box as an ISDN fax machine with an ISDN card from AVM and the hylafax suite.

Translated to English by: Sebastian Bauer <sebastian.baua(at)t-online.de>

Introduction

You don't need much software to use linux for sending faxes over ISDN.

- a root account
- a ISDN card from AVM or an identical modell
- a current kernel (version 2.4.XX) with capi support (I believe that kernel versions 2.2.XX must be patched for capi support)
- the capi4linux drivers from AVM
- the libtiff library
- hylafax

- capi4hylafax
- some patience

I will restrict this article to passive cards from AVM because have only seen capi drivers for Linux for those passiv cards. Besides those cards any active card should work, but I could not test this because I can not afford these (for any hardware charity please contact me). I will compile every program used in this article from source to ensure that this tutorial works for as many Linux distributions as possible. I have tested it with a FritzCard PCI and a ISDN Adaptor Classic (ISA) with SuSE 8.1 and Redhat 8.0 (it worked with these). Unfortunately I cannot guarantee that it works in other configurations.

Kernel settings

For the next steps you MUST have a kernel with capi support, so you should first compile a new kernel. You will find information about compiling a kernel at The Linux Documentation Project e.g. in the kernel HowTo. Many distributions do not include capi support in their kernel or do not use the standard sources, so get the standard kernel source code at www.kernel.org. Besides the kernel settings you need for your hardware you will have to enable the following ISDN specific options:

		ISDN subsystem	ISDN feature submodules		
◇ y	🔶 m 💠 n	ISDN support	→ v ◆ m ↔ n isdnloop support		
🔶 y		Support synchronous PPP			
💠 y		PPP filtering for ISDN	↓ y ◆ m ◇ n Support isdn diversion service		
🔶 y	💠 - 💠 n	Use VJ-compression with s	synchronous PPP		
🔶 y	💠 - 🗇 n	Support generic MP (RFC 1717)			
🗇 у	🔶 m 🗇 n	Support BSD compression			
🔶 y	💠 - 🗇 n	Support audio via ISDN			
🔶 y	💠 - 🗇 n	Support AT-Fax Class 1 and	1 2 commands		
			Active ISDN cards		
	💠 y 🔶 m	🗠 n 🛛 CAPI2.0 support			
	🔶 y 💠 -	Verbose reason cod	reason code reporting (kernel size +=7K)		

• •	\sim	 ✓ " 	verbuse reason code reporting (kernel size +=/K)
🔶 у	÷ -	🗇 n	CAPI2.0 Middleware support (EXPERIMENTAL)
\$у	🔶 m	💠 n	CAPI2.0 /dev/capi support
+ у	\$ -	🗇 n	CAPI2.0 filesystem support
\$у	🔶 m	💠 n	CAPI2.0 capidrv interface support

After that you can compile the kernel as usual with

```
make dep
make bzImage
make modules
make modules_install
```

After that you have to reboot on the new kernel. Now you can go on with the installation of capi4linux.

capi4linux

Officially, the capi4linux device drivers from AVM are only available for SuSE Linux, but you can use them with every other distribution (kernel) you like. First you should download the drivers for your card at www.avm.de. Make sure to get the right drivers for your card. The version of SuSE is almost irrelevant, but it should at least use the same major release version of gcc as you do. Now you can unpack the archive with

tar xfz fcpci-suseX.X-XX.XX.tar.gz

or

tar xfz fcclassic-suseX.X-XX.XX.tar.gz

respectively. Then you can compile the file src.drv/fcpci.o or src.drv/fcclassic.o with

make

in the directory fritz. This file has then to be copied to /lib/modules/2.4.XX/kernel/drivers/isdn/avmb1/. Afterwards you have to do a

depmod

to get the system dependencies right. The error message Unresolved symbols in /lib/modules/2.4.XX/kernel/drivers/isdn/avmbl/fcpci.o that will surely appear can be ignored. To complete the configuration of your ISDN card you have to create the file /etc/capi.conf. The example file from AVM looks like this:

# card	file	proto	io	irq	mem	cardnr	options
#blisa	bl.t4	DSS1	0x150	7	-	-	P2P
#blpci	bl.t4	DSS1	-	-	-	-	
#c4	c4.bin	DSS1	-	-	-	-	
#c4	-	DSS1	-	-	-	-	
#c4	-	DSS1	-	-	-	-	P2P
#c4	-	DSS1	-	-	-	-	P2P
#tlisa	tl.t4	DSS1	0x340	9	-	0	
#t1pci	tl.t4	DSS1	-	-	-	-	
#fcpci	-	-	-	-	-	-	
#fcclassic	-	-	0x300	5	-	-	

Here you have to uncomment the entry for your card. If you use the fcclassic line you probably have to edit it, to match your hardware settings.

capi4k-utils

The capi4k-utils provide some useful tools for the capi interface. To install them you have to get the source code file capi4k-utils-XXX-XX-XX.tar.gz here and then unpack it with

tar xfz capi4k-utils-XXXX-XX-XX.tar.gz

Now you can compile and install the capi4k-utils with

```
cd capi4k-utils
make menuconfig
make
make install
```

You can leave the options at make menuconfig as they are if you are in doubt, but you have to make sure that your changes are consistent with the other settings made later. Now you should add or change the following entries in /etc/modules.conf

```
alias char-major-43 capidrv
alias char-major-44 capidrv
alias char-major-45 capidrv
```

After this preparation you can load the capi modules with

capiinit start modprobe capidrv

and unload them again with

rmmod capidrv capiinit stop

If you get some error messages when you unload the modules - just ignore them! I have written a little startup script to automate this load/unload procedure:

```
#!/bin/bash
#
# System startup script for the isdn-capi subsystem
case "$1" in
     start)
        echo -n "Setting up capi-drivers for ISDN subsystem"
        capiinit start
        modprobe capidrv
        ;;
     stop)
        echo -n "Remove capi-drivers for ISDN subsystem"
        rmmod capidrv
        capiinit stop
        ;;
     restart)
        $0 stop
        $0 start
        ;;
```

```
*)
    echo "Usage:$0{start|stop|restart}"
    ;;
esac
exit 0
```

This script can be copied to /etc/init.d/ or /etc/rc.d respectively and you can use it to load the capi modules automatically at every startup.

libtiff

If you don't have libtiff installed on your system or your libtiff rpm does not provide the needed header files, you will have to compile it from source and install it before you can go on with hylafax. The libtiff package can be downloaded at www.libtiff.org and everything should work fine with

```
tar xfz tiff-vX.X.X.tar.gz
cd tiff-vX.X.X
./configure
make
make install
```

Now you can go on with the installtion of hylafax.

hylafax

To install hylafax you first need the source code from www.hylafax.org. After

```
tar xfz hylafax-X.X.X.tar.gz
```

you must run

```
cd hylafax-X.X.X
./configure
```

At the following Questions you should set the spool directory (option 7) to /var/spool/fax and the paper size (option 13) to A4. You can leave the other setting as they are. After that you must install hylafax with

make install faxsetup

Now you have to use faxsetup to make the right the settings for your area code, international code (both without the leading zeros - they go to Long Distance Prefix and Int. Distance Prefix) and so on. **IMPORTANT:** The last question, the one for

faxaddmodem

has to be answered with NO. After all that you should change the script /etc/init.d/hylafax or /etc/rc.d/hylafax respectively a little. Insert

```
$ECHO "Starting capifax receive..."
/usr/local/bin/c2faxrecv &
```

at the end of the start section and

```
$ECHO "Shutting down capifax receive..."
killall -15 c2faxrecv
```

at the beginning of the stop section. These changes are usefull to start the faxreceive deamon when hylafax is started.

capi4hylafax

hylafax was originally made for "real" modems and therefore you have to install the capi4hylafax patch. This patch makes your ISDN card look like a for hylafax. To install the patch you have to get the tarball at www.avm.de and unpack it with

tar xfz capi4hylafax-XX.XX.tar.gz

Now do

```
cd capi4hylafax-XX.XX.XX
./install
```

to configure and install the patch. The parameters that have to be set are explained in the following table:

	This is the number (without area code) that capi4hylafax uses to send a fax. If Supress MSN is not set to 0 the recipient can also see this number on top of his fax.
Incoming MSN	This is the number (again without region code) that is used to receive faxes. If you want to use more than one number, seperate them by commas.
	These options are needed for operation at a PBX ISDN point-to-point line with direct dial-in (DDI). DDIOffset is the number that precedes, the extension and DDILength is the length of the extension. At IncomingDDIs you can specify a list of used extensions Example: fax number 123456-78 DDIOffset = 123456, DDILength = 2
FaxNumber	This number will be shown to the recipient. Hylafax cannot handle spaces so you should use the form 00XX.XX.XXXXXXXX. The dots will automatically be replaced with spaces.
	Here you can enter your name or company name. This entry will also show up on the faxes that you send out.
NumberPrefix	This option defines the digit required to access an outside line when operating at a PBX (generally "0").

After setting all options as described you should be able to send a fax with

```
c2faxsend -f TIFF -d [TelNum] [TIFF-File]
```

and to receive one with

c2faxrecv -f TIFF

Up to this point you will not need hylafax. The above commands are just a basic check to see that the installation works.

Testing

Now that everything is installed and should work it's time to restart hylafax (/etc/init.d/hylafax restart or something similar) and try to send a fax to somebody.

```
sendfax -n -d [TelNum] [Fax-File]
```

You can use many file formats for the fax-file such as PostScript, PDF or TIFF. When a fax is received c2faxrecv should accept the call and put the fax to /var/spool/fax/recvq as a TIFF file.

Finally...

According to AVM you can use the capi device drivers with only *one* passive ISDN card because e.g. the sending of a fax causes a lot of cpu load. For me sending and receiving faxes worked fine even when I did a kernel compile (Pentium-MMX 166 MHz). There have also been some messages from ambitious ISDN users in de.comp.os.unix.linux.isdn that have successfully used two or more passive cards at once. But all this and also the many possibilities besides the standart that hylafax provides are to much for this article.

I know from my own experience that sending faxes over ISDN is not the easiest task - if you don't know where and how to start it can be really annoying. But I hope that I could help some of you to manage the capi chaos.

All those who tried it - happy faxing...

© Sebastian Bauer "some rights reserved" see	Translation information: de> : Sebastian Bauer <sebastian.baua(at)t-online.de> de> en: Sebastian Bauer <sebastian.baua(at)t-online.de></sebastian.baua(at)t-online.de></sebastian.baua(at)t-online.de>
---	--

2005-01-14, generated by lfparser_pdf version 2.51